

How to prepare P630Pro version 1.3.

New installation

First time the new P630ProV13 is running the program will looking for a valid key.

When found you can see the serial number on left top of screen.

The serial number will be stored locally.

On all P630 systems there are a file where calibration values are stored if used. This file name is p6_xxxx.cfg. Where the xxxx is the last 4 numbers of the serial number. If you use the same key as before you will not get a message that the program not can find this file.

Please copy the old p6_xxxx.cfg file from you system to the location where the new P630Pro programs are stored.

If you do not use the old cfg file do following:

Start the P630 program. Go to Menu->Hw. Mgr.->Hardware Calib. This start the "Hw Soft Calibration

Menu". Click on Ok. This will generate a p6_xxxx.cfg file with default values for your serial number and key.

You need then to calibrate the P630 system. Please read the usermanual.